

OFFICE WORKSTATION DESIGN

No matter what industry you work in, computers are commonly used. Extended work with computers can lead to muscular fatigue and discomfort, usually in the back, arms, shoulders and neck. The risk of a musculoskeletal disorder (MSD) is higher for computer operators than for other office workers. And the risk increases as the intensity of computer work increases.

This document outlines how workstation layout, lighting, and task design can affect the physical and visual demands on people who work with computers. It also provides a checklist to guide your company in what to look for when assessing computer workstations. Using a laptop and other mobile devices as the main computer in an office poses some special challenges. Contact an ergonomist for additional tips and precautions.

Workstation Layout

Keyboard Position

When working at a keyboard, the user should sit in an upright position with the upper arms hanging naturally from the shoulders. The elbows should be bent at about a 90° angle when the fingers are on the home row of the keyboard.

If the keyboard is too high, the user must raise his or her arms and shoulders. This can cause fatigue and discomfort and may increase the risk of injury. If the keyboard is too low, the user has to stoop forward which can stress the arms and the back.

In both cases, the wrists will also be strained. It is important that the equipment is positioned so that the wrists are straight and not bent. Typically, if the keyboard is at the appropriate height, the keyboard legs (if any) should not be raised.



OFFICE WORKSTATION DESIGN

The Mouse

Hand-held input devices, such as a computer mouse, are commonly used in computer work. A mouse should be placed as close to the user's side as possible and at a height that allows the arm to hang relaxed from the shoulder. The wrist should be in a 'neutral' position (that is, so the hand is in line with the forearm). This position causes the least physical stress. The mouse should be able to move freely.

The size and shape of the mouse are also important. For example, to prevent cramped hand postures, different-sized devices may be required for different users. The mouse should also be shaped to minimize bent wrist postures.




Buttons on the mouse should be located to avoid awkward finger and hand postures. Settings can be adjusted for left-handed users and to change the speed and distance of mouse travel and clicking actions required. Users should loosely hold the mouse and move it from the shoulder rather than just the wrist. This distributes muscular demands better and reduces wrist movements and static loading. Alternative input devices are also available such as trackballs, joysticks and digitizing tablets, and may be preferred by some users depending on task, application and/or personal preference.

Monitor Position

Proper positioning of monitors is essential to preventing neck and eye strain. Computer monitors should be placed so that the top of the screen is at, or slightly below, the user's eye level. The viewing distance between the user's eyes and the screen should be 40 to 74 cm.

If the screen is viewed continuously or frequently, it should be directly in front of the worker. For bifocal or trifocal wearers, the top of the screen should be slightly lower (or moved back further) to avoid awkward neck posture. An alternative is to obtain prescription lenses for computer work. Some offices have multiple monitors which pose additional challenges. Contact WSPS for further guidance.



OFFICE WORKSTATION DESIGN

Chair

The purpose of well-designed seating is to provide stable support that allows movement, comfort and task accomplishment. Height-adjustable chairs can help place the user at a proper height for typing, writing and viewing the monitor, especially when height-adjustable tables are not available.

The height of the chair should allow the feet to rest flat on the floor with the thighs roughly parallel to the floor. To place shorter workers at a comfortable typing height, the chair may need to be raised. If a worker's feet cannot reach the floor, provide a footrest. The ankles are usually most comfortable at an angle close to 90°; therefore, footrests can be inclined 0-30°.

No single sitting posture can remain comfortable if maintained for prolonged periods of time. The workstation design, chair design and job organization should all allow for a change in posture. Movement is important to minimize fatigue and static effort of the muscles.

Movement may include slightly altering the angles at the neck, shoulders, elbows, wrists, hips, knees and ankles. In chairs where computer use is the primary task, the seat height, seat angle, backrest height and backrest angle should be adjustable independently of each other. Workers must be made aware of the importance of adjusting their chairs correctly and know how to make the adjustments.



Phone

If the phone is frequently used, it is best not to cradle the phone on the shoulder. To prevent such harmful postures, workers who use a computer while on the telephone for long periods should wear head sets.



OFFICE WORKSTATION DESIGN

Desks


The best way to provide the proper screen and keyboard heights for all users is to use split level tables or desks that allow each height to be adjusted independently. This ensures that almost all users, large and small, can have proper postures as they work. Any table, desk or stand used for computer work must be deep enough for both the keyboard and the monitor to be in front of the worker.

The Canadian Standards Association's Guideline on Office Ergonomics (CAN/CSA Z412-00) recommends a minimum of 76 cm. More space may be required for larger monitors, or less space for flat screens. Keyboard trays and/or monitor risers may also be used to achieve proper positioning. There should also be sufficient leg room: 43 cm of horizontal knee space and 60 cm of toe space.

Document Holders

Computer work often involves entering information from source documents. These should be located beside the screen and in the same plane. Alternatively, 'slant board' document holders position the document between the monitor and the keyboard, thus minimizing the need to rotate the neck. This reduces the amount of head and eye movements between the document and the screen and decreases the risk of muscular and visual fatigue.

The best way to correctly position documents is to use an adjustable document holder. Make sure the holder is suitable for the size and type of documents used in your workplace.



OFFICE WORKSTATION DESIGN

Lighting

Lighting levels from 300 to 500 lux are generally considered to be the most appropriate. However, many offices have twice the level of illumination with few complaints. Sometimes, it is the presence of dark shadows contrasting with the bright computer display that causes eye fatigue. Task lighting and ambient lighting should be balanced to reduce harsh contrast and glare.

Glare is also an important aspect of lighting: it can cause visual fatigue and discomfort and it can force the user to adopt an awkward posture to avoid the glare.

There are different types of glare: direct, indirect and masking:

- Direct glare occurs when there are bright light sources directly in the user's field of view (e.g., windows, etc.).
- Indirect glare occurs when light from windows or overhead lighting is reflected off shiny surfaces in the field of view, such as monitors, desks and other office equipment.
- Light from sources directly overhead causes masking glare on the screen, partly obscuring what the user is trying to focus on.

To reduce glare:

- Use light absorbing curtains and blinds
- Position terminals so the user's line of sight is parallel to windows and overhead fluorescent lights
- Position workstations between rows of overhead lights
- Use parabolic filters on overhead lights (these covers only allow light to travel straight down, not disperse at an angle)
- Use indirect lighting (lighting that reflects off ceilings and walls into the work area)
- As a last resort, use glass or plastic antiglare screens


OFFICE WORKSTATION DESIGN

Task Design

Maintaining any posture over time is fatiguing, no matter how well the workstation is set up. As well, continual data entry or word processing are very repetitive tasks and can further contribute to discomfort and possible injury.

The best remedy is to take frequent breaks from computer work. For example, schedule five minutes of work that does not use the computer for every hour worked. Computer-intensive jobs should be re-designed to include tasks other than computer work.

Organize tasks and set up your workstation so that you can maintain a comfortable upright posture. Items that are required for high frequency tasks, or those with a long duration, should be placed closest to you (the primary zone in the diagram below).



Source: CSA Z412-00 Guideline on Office Ergonomics, Figure 14

Reproduced with the permission of CSA from **Z412-00 (R2005) – Guideline on Office Ergonomics** which is copyrighted by CSA. While use of this material has been authorized, CSA shall not be responsible for the manner in which the information is presented, nor for any interpretations thereof.

OFFICE WORKSTATION DESIGN

Quick Steps for Setting Up Your Computer Workstation

Step #1

- Set the height of the chair so that your thighs are roughly parallel to the floor, with your feet flat on the floor or a footrest
- Your knee angle should be about 100°
- The chair should have a well formed lumbar (lower back) support to help maintain the lumbar curve
- Ensure the chair does not put pressure on the back of the legs
- There should be enough space between the front edge of the seat pan and the back of your knee/lower leg to fit one finger up to one fist

Step #2

- Your elbows should be at an angle of 90°, with your shoulders relaxed and your arms hanging naturally at your sides
- Keep your hands in line with your forearms, so that wrists are straight, not bent up, down or to the side
- The mouse should be directly beside the keyboard

Step #3

- Make sure the arm rests don't interfere with natural movements and/or are adjustable

Step #4

- Set your monitor at a height that allows you to keep your neck straight
- The top of the screen should be at or slightly below eye level

Step #5

- Organize your work so that usual operations are within easy reach
- Place documents beside the monitor on a document holder, or at an angle between the keyboard and monitor

OFFICE WORKSTATION DESIGN

Office Workstation Checklist

Use this checklist to assess your workstation for potential problems. A ‘No’ response may indicate a problem which could lead to a musculoskeletal disorder. Make the necessary changes or adjustments for all potential problems identified. If discomfort persists, you may require advice of an ergonomic specialist.

Office Workstation Item to Check	Y	N	Comments/Possible Adjustments or Changes
1. Chair			
Chair height is appropriate for the individual and work surface height (thighs are parallel to the floor or knees slightly lower than the hips)			
Feet are fully supported on the floor or on a footrest			
Chair has a stable base with five wheels or castors suitable for the floor surface			
The angle of the backrest is adjustable			
The backrest height is adjustable; if not, the backrest supports the inward curve of the lower back			
If armrests are provided, they do not interfere with natural movements			
Chair seat is the appropriate size for the individual			
The seat pan tilt is adjustable (+3° or -4°) for frequent computer users			
There is a space between the front of the chair and the back of your legs (min: width of finger/max: fist)			

OFFICE WORKSTATION DESIGN

Office Workstation Item to Check	Y	N	Comments/Possible Adjustments or Changes
2. Monitor, Keyboard, and Mouse			
The monitor is directly in front of you, if viewed or used regularly			
When keying upper arms are hanging vertical, and lower arms are horizontal (elbows approximately 90°)			
Work is performed directly in front of you, with elbows close to the body			
The wrist is relaxed and not bent. Wrist rests are available			
Mouse is placed on the same level as the keyboard			
Mouse fits comfortably in your hand			
Top of the monitor screen is at or slightly below eye level; lower for bifocal wearers			
The monitor is at a comfortable distance away (40-74 cm)			
Screen is free of glare or shadows			
Windows are not in front or behind the operator			
Letters on the screen are sharp, easy to read, and do not flicker			
3. Work Surface			
Work/writing surface height is about elbow level			
Work surface is large enough to hold all work material			
Frequently used items are within easy reach			
Reaching behind the midline of the body is avoided			
Writing space is available on the individual's dominant side, while on the computer			
Legroom is sufficient to stretch out the legs and to swivel in the chair			
4. Lighting			
Adequate lighting is provided			
You are shielded from glare (e.g., sun or lighting)			
The workstation is located in between rows of overhead lights			

OFFICE WORKSTATION DESIGN

Office Workstation Item to Check	Y	N	Comments/Possible Adjustments or Changes
5. Accessories			
A head set is provided if talking on the phone while keyboarding is regularly required			
If provided, source documents are angled upwards with an appropriate document holder			
Source documents are positioned close to your center of attention if viewed regularly			
Adjustable task lighting is available			
6. Work Practices			
You vary your viewing distance throughout the day by focusing on items further away			
While keyboarding your hands float over the keys, not resting on the wrist rests			
You are able to vary your tasks			
You sit back in the chair properly (head and shoulders are relaxed, not raised, hunched, or rounded), using the backrest for support			
You know how to adjust your chair, and adjust it throughout the day			
You take frequent micro breaks (5 minutes every hour) to change posture and perform stretching exercises			

© Workplace Safety & Prevention Services 2015. Workplace Safety & Prevention Services (WSPS) grants permission to approved end users to reproduce this document in whole or in part, provided its intended use is for non-commercial, educational purposes and that full acknowledgement is given to the WSPS. Approved end users are firms registered with the Workplace Safety and Insurance Board. WSPS reserves the right to extend this permission to other stakeholders and interested parties by express written permission upon application. WSPS extends no warranty to materials amended or altered by the end user. Under no circumstances is this document, or any portion thereof, to be duplicated for purposes of sale or for external reproduction or distribution.

(Sample WSPS acknowledgement, "Reproduced or adapted from name of solution with permission of Workplace Safety & Prevention Services, Mississauga, Ontario.")

The information contained in this reference material is distributed as a guide only. It is generally current to the best of our knowledge as at the revision date, having been compiled from sources believed to be reliable and to represent the best current opinion on the subject. No warranty, guarantee, or representation is made by WSPS as to the absolute correctness or sufficiency of any representation contained in this reference material. WSPS assumes no responsibility in connection therewith; nor can it be assumed that all acceptable safety measures are contained in this reference material, or that other or additional measures may not be required in particular or exceptional conditions or circumstances.

Revised: April 2015